

9-1971

Tips for Small Grain Seeding

Morris J. Bitzer
University of Kentucky

James H. Herbek
University of Kentucky, james.herbek@uky.edu

Dennis M. TeKrony
University of Kentucky

Follow this and additional works at: https://uknowledge.uky.edu/pss_notes



Part of the [Agronomy and Crop Sciences Commons](#)

[Right click to open a feedback form in a new tab to let us know how this document benefits you.](#)

Repository Citation

Bitzer, Morris J.; Herbek, James H.; and TeKrony, Dennis M., "Tips for Small Grain Seeding" (1971).
Agronomy Notes. 127.
https://uknowledge.uky.edu/pss_notes/127

This Report is brought to you for free and open access by the Plant and Soil Sciences at UKnowledge. It has been accepted for inclusion in Agronomy Notes by an authorized administrator of UKnowledge. For more information, please contact UKnowledge@lsv.uky.edu.

*CROPS
*SOILS

UNIVERSITY of KENTUCKY • COLLEGE of AGRICULTURE

AGRONOMY NOTES

DEPARTMENT of AGRONOMY ————— Lexington 40506

Vol. 4, No. 7

TIPS FOR SMALL GRAIN SEEDING

September, 1971

Morris J. Bitzer and James Herbek
Extension Specialist in Grain Crops,
and Dennis TeKrony, Extension Specialist in Seed Technology

1. TEST YOUR SOIL AND SUPPLY THE SUGGESTED LIMING AND FERTILIZER MATERIALS. A soil test is the first step to profitable small grain production. A pH of 6.0 to 6.5 is best, and nitrogen should be applied both in the fall and spring. If your small grains are part of a double cropping system the P and K requirements for both crops should be applied in the fall.

2. PROPER SEEDBED PREPARATION. The seedbed should be shallow, fairly smooth, and firm. A properly prepared seedbed will permit uniformity of seeding depth. Disking to a depth of 2 to 4 inches is usually all that is necessary when following other row crops.

3. PROPER SEEDING DEPTH AND SEEDING RATE. Seeding depth is important because small grains need strong root systems at the proper depth to withstand winter "heaving" of the soil. Seed should be planted from 1 to 2 inches deep, depending on soil and moisture conditions.

	Seeding Rate Per Acre	
	For grain	For forage
Wheat and Rye	1 - 1½ bushels	2 - 2½ bushels
Barley	1½ - 2 bushels	3 bushels
Oats	2 - 3 bushels	3½ bushels

4. SEED SOURCE AND VARIETY SELECTION. Good stands are the result of planting good seed. Choose seed that is:

True to variety	Free from weed seeds and crop mixtures
Highly germinative (90% or better)	Chemically treated

Planting certified seed is the surest way to obtain these qualities.

	<u>Varieties</u>		<u>Varieties</u>
Wheat	Arthur, Benhur Blueboy, Knox 62 Monon, Redcoat	Oats, Spring	Brave
		Winter	Compact Norline Walken
Barley	Barsoy, Knob Harrison, Dayton Jefferson	Rye	Balbo

5. SEEDING DATE. Small grains often fail because they are seeded too late. Seeding should be early enough to establish a good root system before a heavy freeze.

Recommended Seeding Dates

	<u>For grain</u>	<u>For forage</u>
Wheat	Oct. 1 - 20	Sept. 15 - Oct. 1
Barley	Sept. 15 - Oct. 10	Sept. 1 - 20
Oats, Winter	Sept. 15 - Oct. 10	Sept. 1 - 20
Spring	Feb. 15 - Mar. 15	
Rye	Oct. 1 - 15	Sept. 1 - 30

6. AERIAL SEEDING OF SMALL GRAINS. Seeding rates should be increased by 30 to 50 percent for aerial seeding. The ideal time for aerial seeding in soybeans is just before the big lower leaves of the plants fall. Barley, oats, and rye should be planted in September and wheat seedings completed in October.

7. DOUBLE CROPPING. Use your small grains for grain or forage and follow with a second crop such as corn, soybeans, or grain sorghum. Selection of the earliest maturing varieties is most important in a double cropping system. Apply the necessary requirements of P and K for both crops in the fall.

8. DISEASE CONTROL. The major diseases in small grains are the smuts and rusts. If smuts have been a problem, planting certified seed is the best way to control this disease. Rusts are most easily controlled by growing resistant varieties.